Configuring Windows 7 for the Augustana Wireless Network

Follow these instructions to connect a Windows 7 computer to the Augustana wireless network.

- 1. Click the Windows (Start) button and then click Control Panel.
- 2. Click Network and Internet and then click Network and Sharing Center.
- 3. Click Manage wireless networks.

6

4. Click Add and then click Manually create a network profile.

) 💷 Manu	ually connect to a wireless network	
How d	o you want to add a network?	
2	Manually create a network profile This creates a new network profile or locates an existing network and saves a prof for the network on your computer. You need to know the network name (SSID) as security key (if applicable).	ile nd
4	Create an ad hoc network This creates a temporary network for sharing files or an Internet connection	
		Cancel

5. Enter the following information:

Network name: "AugustanaWiFi(Secured)" Security type: "WPA2-Enterprise" Encryption type: "AES"

_		
🚱 💷 Manually connect to	a wireless network	
Enter information f	or the wireless network you want to add	
N <u>e</u> twork name:	AugieWiFi(Secured)	
<u>S</u> ecurity type:	WPA2-Enterprise	
Encryption type:	AES	
Se <u>c</u> urity Key:	Hide characters	
☑ S <u>t</u> art this connect	on automatically	
Connect even if the	e network is not broadcasting	
Warning: If you se	elect this option, your computer's privacy might be at risk.	
	N	ext Cancel

- 6. Click Next and then click **Change connection settings**.
- 7. Click on the **Security** tab.

nnection Security				
Security type:	WPA2-Enterp	rise		•
Encryption type:	AES			•
Microsoft: Protecte	d EAP (PEAP)	[Settings	
Microsoft: Protecte Remember my cr time I'm logged o	d EAP (PEAP) edentials for this n	connection	Settings n each	
Microsoft: Protecte	d EAP (PEAP) edentials for this n	connectio	Settings n each	

- 8. Click the **Settings** button.
- 9. Uncheck Validate server certificate.

tected EAP Prop	erties		
hen connecting:	45		
Validate server	r certificate		
Connect to th	ese servers:		
Trusted Root Cer	tification Authoriti	es:	
Class 3 Public	Primary Certificat	tion Authority	
Entrust.net S	Secure Server Cert	dification Authority	
Equifax Secu	re Certificate Auth	nority	E
GlobalSign Ro	oot CA		1
GTE CyberTr	ust Global Root		
Microsoft Ro	ot Authority		
Microsoft Ro	ot Certificate Auth	ority	-
4	ш		- F
certification a	n Method:)	Configure.
Enable Fast Rec Enforce Network Disconnect if ser Enable Identity	onnect Access Protection wer does not pres Privacy	n ent cryptobinding	τιν
		ОК	Cancel

- 10. Click the **Configure...** button.
- 11. Uncheck Automatically use my Windows logon name and password (and domain if any).



- 12. Click ${\bf OK}$ and then click ${\bf OK}$ again.
- 13. Click Advanced settings.

14. Check Specify authentication mode: and select User authentication.



15. Click **OK**.

Note: If you want Windows to remember your username and password, check the box next to "Remember my credentials for this connection each time I'm logged on". Note: After you change your Augustana password, you will be prompted to enter your username and new password when you connect to the wireless network.

enterprise
ion method:
ion method: IP)
or this connection each

- 16. Click **OK**, and then click **Close**.
- 17. <u>Click on the wireless network icon in the system tray (in the lower-right corner of the screen)</u>.



18. Click **Augustana** and then click **Connect**.

Not connected	43 ^
Connections are available	
Dial-up and VPN	^
Augie VPN	×
Wireless Network Connection	<u>∧</u> ≡
AugieWiFi(Secured)	التر
Connect automatically	onnect
ACGuestNet	<u>.</u>
AugieWiFi	S al
augustana	S ul
HP4D5A73	🔥 🔻
Open Network an Signal St Security	rength: Good Type: Unsecured
Radio Ty	/pe: 802.11g gustana

19. Enter your username and password when prompted and click **OK**.

Windows Security	
Network Au Please enter us	uthentication er credentials
	User name Password
	OK Cancel

20. You will be connected to the Augustana wireless network.